

GNU Proxyknife 1.6

The customizable proxyhunter
Updated for Proxyknife 1.6, 17 November 2006

by Jia Wang

Copyright © 2005-2006 Jia Wang

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

Table of Contents

1	Introduction	1
2	Invoking	2
2.1	Command-line Exclusive Options	2
2.2	Startup Options	2
3	General Usage	6
4	Download Proxylist	7
5	Via Proxy	8
6	Customize Request	9
7	Startup File	10
7.1	Examples of startup file	10
8	Sort the Result	14
9	Scripts	15
10	Proxylist	16
11	Output	17
12	Contact	20
Appendix A	Copying This Manual	21
A.1	GNU Free Documentation License	21
A.1.1	ADDENDUM: How to use this License for your documents	27
	GNU General Public License	28
	Index	33

1 Introduction

GNU Proxyknife is a customizable multithread *proxy hunter*. It can help users after strict firewall find suitable free proxies.

GNU Proxyknife reads *proxylist*¹ from the file, stdin or the web, then validates the free proxies and prints the good ones. Time intervals and the others which are useful to estimate the speed or capability of every proxy are also printed. The whole processing can be customized by the user, which is different from the other hunters.

In URL mode, Proxyknife can read a large number of proxies on machines with few memory. It works on GNU/Linux, SunOS, OSF1 or more.

As a proxy hunter, Proxyknife can validate all kinds of proxies with different methods: HTTP proxy with GET or CONNECT method, SOCKS5 proxy with CONNECT command, SOCKS4 proxy with CONNECT command. As a customizable extension, it can check proxies for special purpose, such as finding tunnels for MSN chatting.

Proxyknife can check proxies via a tunnel. The tunnel can be SOCKS4 proxy, SOCKS5 proxy or HTTP proxy, with or without authentication for the latter two. The route from the local machine that proxyknife runs on to *checksite* is:

```
proxyknife ----- (myproxy) ----- testproxy ----- checksite
```

Here *myproxy* is the tunnel, *testproxy* is the free proxy being checked and *checksite* is the site used to validate free proxies.

Proxyknife have many features. Please see the file 'FEATURELIST' included in this package for details.

¹ The list of free proxies.

2 Invoking

Invoke `proxyknife` like this:

```
./proxyknife [OPTION]...
```

If `proxyknife` is invoked without arguments, it will read `proxylist` from the file named `'proxylist'` in the current directory. The result will be written to a file named `'proxyout'` in the current directory, together with the verbose output on screen.

To change the default parameters, switch the mode or invoke it for special purpose, you can do it in two ways: permanently, add the setting to the `'start file'` (see [Chapter 7 \[Startup File\]](#), page 10), or specifying it on the command line. You can also specify the `'startup file'` (see [Chapter 7 \[Startup File\]](#), page 10) on the command line.

Some constants in the source code:

```
#define HTTP_GET 0
#define HTTP_CONNECT 1
#define SOCKS5_CONNECT 2
#define SOCKS4_CONNECT 5
#define HTTP_CONNECT_AUTH 11
#define SOCKS5_CONNECT_AUTH 12
#define DIRECT 21
#define IN_FILE 0
#define IN_HTTP 1
#define LOGSTDERR "."
```

Please use the value but not the former string on command line or in `'startup file'` (see [Chapter 7 \[Startup File\]](#), page 10).

2.1 Command-line Exclusive Options

`'-v'`

`'--version'`

Display the version of Proxyknife and exit.

`'--help'` Print all command-line options.

`'-f file'` Use `file` as `'startup file'` (see [Chapter 7 \[Startup File\]](#), page 10). Without this option, `proxyknife` will try `'./proxyknife.conf'`, then `'$HOME/.proxyknife.conf'`, at last `'$prefix/etc/proxyknife.conf'`¹.

2.2 Startup Options

Anyone of the following options have a `'keyword'` form which can be specified in `'startup file'` (see [Chapter 7 \[Startup File\]](#), page 10). In this section, every single option is followed by a `'keyword'`.

If you have duplicate options on command line or settings in `'startup file'` (see [Chapter 7 \[Startup File\]](#), page 10), only the first one will be used. Anyway, do not let this happen if possible.

`'-d'`

`'debug'` Turn on debug output.

Argument after this option is not required and should be completely omitted on command line. If this option exists, the value will be set to 1 automatically.

¹ `$prefix` is the argument passed to the configure script: `'./configure --prefix=/some/path'`. It is `'/'` by default.

While in startup file, use `'debug=1'` to turn on debug output. `'debug=0'` to disable it. The value is `0` by default.

`'-t threads'`

`'threads'` The number of threads opened at the same time. This should be based on the resource available on your system. The number can't be more than 65535. On the other hand, though nocache header is used, running proxyknife with less threads may give more accurate result. Default: `50`.

`'-g user_agent'`

`'user_agent'`

Identified as browsers or other clients. Default: `'User-Agent: MSIE 6.0'`

`'-I proxyknifetype'`

`'proxyknifeintype'`

The mode of input. `0`: file mode, `1`:url mode. In file mode, proxyknife will regard the value of keyword `'proxyknifein'` or the argument after option `'-i'` as filename; otherwise, in url mode, they are parsed as part of URL. Now only two sites are available in url mode: `proxylist.kmip.net/list.html` and `youth.bupt.edu.cn/proxy/`.

By default, proxyknife will read file `'proxylist'` in current directory in file mode and fetch proxylist from `http://proxylist.kmip.net/list.html` in url mode.

Default: `0`

`'-i proxyknifein'`

`'proxyknifein'`

The input filename with full path which proxyknife read proxylist from or the url to the proxylist file. Let it be `"-"` to read from stdin. In url mode, this value can be `'proxylist.kmip.net/list.html'` or `'youth.bupt.edu.cn/proxy/'`. I haven't try the other sites. In url mode, proxyknife may connect to the web via `myproxy`, which is based on the value of `'mytype'`. Default: `'proxylist'` or `'proxylist.kmip.net/list.html'`

`'-m mytype'`

`'mytype'`

The type of myproxy. If enabled, proxyknife will send all request via it. It should be enabled for lan users after a proxy tunnel. The value can be: `1` (HTTP_CONNECT - HTTP proxy without authentication), `2` (SOCKS5_CONNECT - socks5 proxy without authentication), `5` (SOCKS4_CONNECT - socks4 proxy without authentication), `11` (HTTP_CONNECT_AUTH - HTTP proxy with basic authentication), `12` (SOCKS5_CONNECT_AUTH - socks5 proxy with username/password authentication), `21` (DIRECT - Disabled, connect to `testproxy` directly). Default: `21`

`'-h myhost'`

`'myhost'`

The IPV4 address or host name of myproxy. This will be in effect only if `mytype !=21` Default: `NULL`²

`'-p myport'`

`'myport'`

The port of myproxy. This will be used if `mytype !=21` Default: `NULL`

`'-u myuser'`

`'myuser'`

The username for myproxy. This will be used only if `'mytype'=11` or `12`. Default: `NULL`

`'-s mypass'`

`'mypass'`

The password for myproxy. This will be used only if `'mytype'=11` or `12`. Default: `NULL`

² In this section, `'NULL'` means there is no default value for that keyword.

`-c checksite`
`checksite`
 The site used to check testproxies. Default: `http://www.google.com:80/webhp?hl=en`

`-C checkreqin`
`checkreqin`
 The file including the customized request. Default: `NULL`

`-k key`
`key`
 The string that should be found in the response after a successful request to the *checksite*. Default: `2006 Google`

`-r rcvtimeo`
`rcvtimeo`
 The socket receiving timeout in seconds. Default: `10`

`-n sndtimeo`
`sndtimeo`
 The socket sending timeout in seconds. Default: `5`

`-S myconreplysize`
`myconreplysize`
 The size of buffer used to store the reply after sending CONNECT request for testproxy to myproxy. This is used for some weird proxies. Please leave it intact if unsure. Default: `256`

`-T testconreplysize`
`testconreplysize`
 The size of buffer used to store the reply after sending CONNECT request for *checksite* to testproxy. It is only be used when you validate HTTP CONNECT proxies. Just as above, do not change it if unsure. Default: `256`

`-G testtagreplysize`
`testtagreplysize`
 The size of buffer used to store the reply after sending GET request to the *checksite*. Proxyknife will try to find the *key* from this buffer. Default: `65535`

`-H httpstestmethod`
`httpstestmethod`
 The HTTP method sent to the *testproxy*. The possible values are 0 (HTTP_GET) and 1 (HTTP_CONNECT) now. If you need a HTTP proxy supporting CONNECT, just set it to 1. Default: `0`

`-5 socks5testmethod`
`socks5testmethod`
 The socks5 command used in the interaction with the *testproxy*. Only 2(SOCKS5_CONNECT) is implemented. You should leave it intact now. Default: `2`

`-4 socks4testmethod`
`socks4testmethod`
 The socks4 command used in the interaction with the *testproxy*. Only 5(SOCKS4_CONNECT) is implemented. You should leave it intact now. Default: `5`

`-l logfile`
`logfile`
 The logfile with full path. If you prefer screen output, use a single `'.'` (`'.'` is just before `(LF)`) to leave stderr as it is:

```
proxyknife -l .
```

or add this to startup file:

```
logfile=.
```

If you want to see it laterly:

```
proxyknife -l ./proxyknife.log
```

or add this to startup file:

```
logfile=./proxyknife.log
```

Default: 'proxyknife.log'

'-o *proxyknifeout*'

'proxyknifeout'

The output file with full path. Proxyknife print result to this file. If you do not specify it, proxyknife will use a file named 'proxyout' in the current directory. If this file do not exists, proxyknife will creat it. Otherwise, it will be overridden.

Default: 'proxyout'

3 General Usage

Read the proxylist from local file `‘/tmp/mylist.txt’`:

```
proxyknife -i /tmp/mylist.txt
```

Do the same with 100 threads:

```
proxyknife -i /tmp/mylist.txt -t 100
```

Find http proxy supporting CONNECT:

```
proxyknife -i /tmp/mylist.txt -H1
```

Find http proxy supporting ftp with GET method:

```
proxyknife -i /tmp/myhttplist.txt -c 'ftp://somesite/' -k 'pub'
```

Print the result to a file named `‘myoutput.txt’`

```
proxyknife -i /tmp/mylist.txt -o myoutput.txt
```

Check the newlist again with CONNECT checking for the HTTP proxies:

```
proxyknife -i ./myoutput.txt -H1
```

Identify as firefox 2.0:

```
proxyknife -g 'Mozilla/5.0 (X11; U; Linux i686; en-US; rv:1.8.1) Gecko/20061010 Firefox'
-i /tmp/mylist.txt
```

Print more to screen:

```
proxyknife -i /tmp/mylist.txt -o . -d
```

Tips:

1. You can type `Control-c` to stop proxyknife at any time without losing the result.
2. You can create several `‘startup files’` (see [Chapter 7 \[Startup File\]](#), page 10) to fit for different need and invoke them with `‘-f’` option.
3. For default installation, proxyknife use `‘/etc/proxyknife.conf’` as `‘startup file’`. For all users, you can create `.proxyknife.conf` at their home directories. Thus they will have their own default `‘startup files’`, independent of `‘/etc/proxyknife.conf’`.

4 Download Proxylist

As a test, proxyknife can download the *proxylist* from the web automatically and extract the proxylist embed in the web. After the download is completed, the validating begin. Now only two sites are supported:

Using <http://proxylist.kmip.net/list.html>.

```
proxyknife -I1
```

Using <http://youth.bupt.edu.cn/proxy/>.

```
proxyknife -I1 -i 'youth.bupt.edu.cn/proxy/'
```

5 Via Proxy

- If you have a HTTP proxy (hostname:*myproxy.com*, port:*8080*, used as *myproxy*) with basic authentication (username:*userabc*, password:*pass12345*), you want to download proxylist from <http://youth.bupt.edu.cn/proxy/> via this proxy and validate the free proxies via the same HTTP proxy:

```
proxyknife -I1 -i 'youth.bupt.edu.cn/proxy/' -m11 \
-h myproxy.com -p 8080 -u userabc -s 'pass12345'
```

Is it too long? Then write these to startup file (see [Chapter 7 \[Startup File\]](#), page 10):

```
mytype=11
myhost=myproxy.com
myport=8080
myuser=userabc
mypass=pass12345
proxyknifeintype=1
proxyknifein=youth.bupt.edu.cn/proxy/
```

After that, invoke `proxyknife` without arguments will do the same thing:

```
proxyknife
```

- If you have a HTTP proxy (*myproxy.com:8080*) without authentication, do it like this:


```
proxyknife -I1 -i 'youth.bupt.edu.cn/proxy/' -m1 -hmyproxy.com -p 8080
```
- If your *myproxy* is a SOCKS4 tunnel with host name '*myproxy.com*', port '*1080*' and you can reach <http://proxylist.kmip.net/list.html> via it:


```
proxyknife -I1 -m5 -hmyproxy.com -p1080
```
- If your *myproxy* is a SOCKS5 tunnel with host name *myproxy.com*, port *1080*. You hope `proxyknife` reads proxylist from the local file named '`proxylist`' and validates via *myproxy*:


```
proxyknife -m2 -hmyproxy.com -p1080
```
- If your *myproxy* (*myproxy.com:1080*, *userabc:pass123*) is a SOCKS5 tunnel based on username/password authentication with host name '*myproxy.com*', port '*1080*', you can invoke `proxyknife` like this to do the same thing:


```
proxyknife -m12 -hmyproxy.com -p1080 -u'userabc' -p'pass123'
```

6 Customize Request

Proxyknife can send customized request, that is to say, you can even check some unknown services with it.

I write a sample file named `msn.req`, which is included in this package. With this file, you can check whether a proxy can work as a MSN tunnel, that is to say, whether you can do MSN chatting via that proxy.

```
proxyknife -I1 -H1 -c messenger.hotmail.com:1863 -C msn.req -k 'cat msn.req'
```

7 Startup File

Every Startup Option (see [Section 2.2 \[Startup Options\]](#), page 2) can be added to ‘startup file’ using the ‘keyword’ listed after it on that section (see [Section 2.2 \[Startup Options\]](#), page 2).

For instance, you can replace ‘-t 20’ with the setting:

```
threads=20
```

Then you can remove ‘-t 20’ from the command line.

The syntax of startup file:

1. The data is in the form of ‘keyword=value’, start from the beginning of that line.
2. Write ‘keyword=value’ in a single line.
3. All characters will be parsed except `\n`. **Please do not add redundant whitespace or quotation mark, they will be read as part of ‘keyword=value’ pair.** But it is permitted to use whitespace or quotation mark in ‘value’ if it is really needful:

```
user_agent=User-Agent: MSIE 6.0
```

4. Comment line *begin* with ‘#’. Certainly, the line begins with string different from anyone of the startup keywords (see [Section 2.2 \[Startup Options\]](#), page 2) will be identified as comment line or ignored.

If you invoke proxyknife with a startup option (see [Section 2.2 \[Startup Options\]](#), page 2), the setting relation to it in ‘startup file’ will be overridden.

By default, proxyknife will search the startup file in this order until one of them is found:

1. ‘./proxyknife.conf’
2. ‘\$HOME/.proxyknife.conf’
3. ‘\$prefix/etc/proxyknife.conf’

You can invoke proxyknife with ‘-f ‘startup file’’ (see [Section 2.2 \[Startup Options\]](#), page 2) to override that:

```
proxyknife -f /tmp/mystartup.txt
```

7.1 Examples of startup file

- Conditions: A direct connection to <http://proxylist.kmip.net/list.html>.

Want to validate: Free HTTP proxy supporting CONNECT method, free SOCKS5 or SOCKS4 proxy supporting CONNECT command.

Your ‘startup file’ should look like this:

```
#Connect to proxies to be checked directly.
#For http proxies, try to check with connect method.
mytype=21
httptestmethod=1
proxyknifeintype=1
```

- Conditions: A HTTP proxy(‘www.myhttptunnel.com:8080’,supporting CONNECT method) with basic authentication . The username is ‘abc’, the password is ‘123’. A connection to <http://youth.bupt.edu.cn/proxy/> or free proxies can be done via this HTTP proxy.

Want to validate: Free HTTP, SOCKS5 or SOCKS4 proxy that can be used as *MSN tunnel*.

The content of your ‘startup file’ will be:

```
#Check http,socks5,socks4 proxies with customized request: msn.req.
#Check is done via a tcp tunnel(http proxy).
mytype=11
myhost=www.myhttptunnel.com
myport=8080
myuser=abc
mypass=123
httptestmethod=1
checksite=messenger.hotmail.com:1863
checkreqin=msn.req
key=VER 0 MSNP8 CVRO
proxyknifeintype=1
proxyknifein=youth.bupt.edu.cn/proxy/
```

- Conditions: A HTTP proxy('www.somehttpproxy.com:8080') without authentication. A connection to free proxies can be done via this HTTP proxy. A file named 'proxylis' including the list of free proxies is in the current directory.

Want to validate: Free HTTP proxy with common GET method, SOCKS5 or SOCKS4 proxy with CONNECT command.

You can write these to your 'startup file':

```
#Check http proxies with GET method.
#Checking is done via a tcp tunnel(here http proxy).
mytype=1
myhost=www.somehttpproxy.com
myport=8080
```

- Conditions: A SOCKS5 proxy ('socks.you.com') with username/password authentication. The port of socks5 service is 1080, the username is 'phc', the password is '678'. The connection to <http://youth.bupt.edu.cn/proxy/> or free proxies can be done via this SOCKS5 tunnel.

Want to validate: Common free HTTP proxy, free socks5 or socks4 proxy which support connect command.

Your setting should be similiar with this:

```
#Find http proxies with GET method, socks4/socks5 proxies with connect cmd
#All is done via a tcp tunnel(socks5 proxy) with username/password auth.
mytype=12
myhost=socks.you.com
myport=1080
myuser=phc
mypass=678
proxyknifeintype=1
proxyknifein=youth.bupt.edu.cn/proxy/
```

- Here is the default 'startup file' full of comments:

```
#The number of threads
#threads=50
#Turn on debug1 to debug, 0 to disable it.
#debug=0
#The meaning of some constants(These aren't keyword, only reference):
#define HTTP_GET 0
#define HTTP_CONNECT 1
#define SOCKS5_CONNECT 2
#define SOCKS4_CONNECT 5
```

```
#Send CONNECT request to http proxy with authentication
#define HTTP_CONNECT_AUTH 11
#Send CONNECT request to socks5 proxy with authentication
#define SOCKS5_CONNECT_AUTH 12
#Do not use myproxy
#define DIRECT 21
#The value of mytype must be 1,2,5,11,12 or 21 now, as defined above
#mytype=21
#myhost=www.somehttpproxy.com
#myport=8080
#Authenticate
#myuser=username
#mypass=password
#The site used to validate free proxies
#checksite=http://www.google.com:80/webhp?hl=en
#For msn
#checksite=messenger.hotmail.com:1863
#key=2006 Google
#For msn
#key=VER 0 MSNP8 CVR0
#Some references
#define HTTP_GET 0
#define HTTP_CONNECT 1
#define SOCKS5_CONNECT 2
#define SOCKS4_CONNECT 5
#The value of httpstestmethod can only be 1 or 0 now.
#httpstestmethod=0
#Must be 2 now, do not change it
#socks5testmethod=2
#Must be 5 now, do not change it
#socks4testmethod=5
#Size of buffer used to receive reply after sending CONNECT req to myproxy
#myconreplysize=256
#Size of buffer used to receive reply after sending CONNECT req to testproxy.
#testconreplysize=256
#The size of buffer used to store data from the target. Key was searched in it.
#testtagreplysize=65535
#Identify as
#user_agent=User-Agent: MSIE 6.0
#Specify the receiving timeout, in seconds, 0 to disable
#rcvtimeo=10
#Specify the sending timeout, in seconds, 0 to disable
#sndtimeo=5
##define LOGSTDERR "."
#Redirect stderr to log file. Use "." to leave stderr as it is.
#logfilename=.
#logfilename=proxyknife.log
#Reference
#define IN_FILE 0
#define IN_HTTP 1
#The type of proxyknifein or the mode of Proxyknife. 0:file,1:http.
#proxyknifeintype=0
```

```
#The proxylist file or url with full path
#File mode:
#proxyknifein=proxylist
#Read from stdin:
#proxyknifein=-
#In url mode, only these two sites are tested. Select one of them.
#proxyknifein=proxylist.kmip.net/list.html
#proxyknifein=youth.bupt.edu.cn/proxy/
#Print the result to this file with full path
#proxyknifeout=proxyout
#Customize the request
#checkreqin=msn.req
```

8 Sort the Result

Here is a sample of the result (The result is included in ‘proxyout’ by default):

```
222.216.109.55:3128@HTTTPC 0.032189 0.126676 0.161449 0.034833 HTTP:GET
64.34.113.100:80@HTTTPC 0.372466 0.367725 1.555638 0.375829 HTTP:GET
59.41.253.35:80@HTTTPC 0.025951 4.463531 0.687924 1.077910 HTTP:GET
```

The format is described in section Output (see [Chapter 11 \[Output\]](#), page 17).

Now type ‘bash’, then you can sort the result like the following:

- To sort by the response speed:

```
sort -nk 4 proxyout
```

The output:

```
222.216.109.55:3128@HTTTPC 0.032189 0.126676 0.161449 0.034833 HTTP:GET
59.41.253.35:80@HTTTPC 0.025951 4.463531 0.687924 1.077910 HTTP:GET
64.34.113.100:80@HTTTPC 0.372466 0.367725 1.555638 0.375829 HTTP:GET
```

- To sort by the transfer speed: (This is not accurate for response with small data)

```
sort -nk 5 proxyout
```

The output:

```
222.216.109.55:3128@HTTTPC 0.032189 0.126676 0.161449 0.034833 HTTP:GET
64.34.113.100:80@HTTTPC 0.372466 0.367725 1.555638 0.375829 HTTP:GET
59.41.253.35:80@HTTTPC 0.025951 4.463531 0.687924 1.077910 HTTP:GET
```

- To sort by the total delay:

```
cat proxyout |while read proxy a b c d req;\
do echo $proxy $a $b $c $d 'echo $a+$b+$c+$d|bc' $req;done |\
sort -nk 6
```

The output:

```
222.216.109.55:3128@HTTTPC 0.032189 0.126676 0.161449 0.034833 .355147 HTTP:GET
64.34.113.100:80@HTTTPC 0.372466 0.367725 1.555638 0.375829 2.671658 HTTP:GET
59.41.253.35:80@HTTTPC 0.025951 4.463531 0.687924 1.077910 6.255316 HTTP:GET
```

9 Scripts

Replace `user_agent` with another HTTP header, such as `Cookie`:

```
proxyknife -g 'Cookie: var=value; var2=something'
```

Create proxylist on-the-fly. In this example proxyknife scans free proxies with ip ranging from 127.0.0.1 to 127.0.0.254, the checked port is 3128:

```
bash
$ for ((i=1;i<255;i++));do echo 127.0.0.$i:3128@HTTP;done|proxyknife -i -
```

With the customized request, you can do more things.

SSH scan:

```
echo "127.0.0.1:22"|proxyknife -i- -I0 -H0 -C ssh.req -k mismatch
```

Do the same scan via the free proxy 127.0.0.5:

```
echo "127.0.0.5:3128"|proxyknife -i- -I0 -H1 -C ssh.req -c 127.0.0.1:22 -k mismatch
```

10 Proxylist

The content of proxylist should be like this:

```
ip:port@proto.*
```

or

```
ip:port
```

I remove support on domain, so ip must be IPV4 address. The port must be integer range from 1 to 65535. The proto can only be HTTP,http,socks5,SOCKS5,socks4 or SOCKS4. All of the chars afterproto will be ignored.

If there is no @ or other chars after the port in the line,proto is regarded as HTTP by default.

Example:

```
61.132.89.130:80@HTTP  
202.123.52.156:8080
```

11 Output

Every line of the result is in the form of 'host:port@PROTOCOLMETHOD *estab pcon end req*'. A sample of the output:

```
222.216.109.55:3128@HTTPC 0.032189 0.126676 0.161449 0.034833 HTTP:GET
64.34.113.100:80@HTTPC 0.372466 0.367725 1.555638 0.375829 HTTP:GET
59.41.253.35:80@HTTPC 0.025951 4.463531 0.687924 1.077910 HTTP:GET
```

By default, proxyknife use the default testmethod, the req field will be filed with 'HTTP:GET' now. If you use your own testmethod with '-C msn.req' (see [Section 2.2 \[Startup Options\], page 2](#)) (see [Chapter 6 \[Customize Request\], page 9](#)) on command line or 'checkreqin=msn.req' in 'startup file' (see [Chapter 7 \[Startup File\], page 10](#)), this field will be filled with the argument or value, the filename of the request file, which is 'msn.req' in this case.

The current version of proxyknife output timeouts of every steps of validation:

Method	Output (time increase ->)
HTTP_GET	host:port@HTTPG <i>estab</i> 0 <i>pget</i> <i>end req</i>
HTTP_CONNECT	host:port@HTTPC <i>estab pcon</i> <i>get</i> <i>end req</i>
SOCKS5_CONNECT	host:port@SOCKS5C <i>estab pcon</i> <i>get</i> <i>end req</i>
SOCKS4_CONNECT	host:port@SOCKS4C <i>estab pcon</i> <i>get</i> <i>end req</i>

The chart of validating:

```
Proxyknife -- (myproxy) --- testproxy -- target(checksite)
ta ----->
      estab = tb - ta
tb <-----
tc ----->
      pcon = td - tc  HTTP_CONNECT,SOCKS5_CONNECT or SOCKS4_CONNECT.
td <-----
te ----->
      (p)get = tf - te  get:HTTP_CONNECT,SOCKS5_CONNECT,SOCKS4_CONNECT,
                       pget:HTTP_GET
tf <-----
tg ----->
      end = th - tg
th <-----
```

The meaning of symbols in the chart:

symbol	meaning
-	start to send, the left string is time.(such as ta)
<-	The data entered,the left string is the time when data come in.
ta tb tc td te tf tg	coordinate time in seconds during a single validating

delay	define
<i>estab</i>	Delay from the time(ta) proxyknife send CONNECT request for <i>testproxy</i> to <i>myproxy</i> (or begin to connect to <i>testproxy</i> directly) to the time(tb) it receives 'Connection Established'(or the connection to <i>testproxy</i> is completed).

<i>pcon</i>	Delay from the time(tc) proxyknife send CONNECT request for <i>checksite</i> to <i>testproxy</i> to the time(td) it receives 'Connection Established'. With HTTP_GET method, it is impossible to get <i>pcon</i> , which is included in <i>pget</i> delay.
<i>get</i>	Delay from the time(te) proxyknife send HTTP GET request for <i>checksite</i> to <i>testproxy</i> to the time(tf) it receives the first byte data returned. Exclusive for HTTP_GET method.
<i>pget</i>	Delay from the time(te) proxyknife send GET request for <i>checksite</i> to <i>testproxy</i> to the time(tf) it receives the first byte data returned.
<i>end</i>	Delay from the time(tg or tf) proxyknife receive the first byte data to the time(th) it receives data including <i>key</i> .

If we define 'TP' as 'testproxy', 'TG' as 'checksite', then we got the 'approximate mathematics' of the delays:

```

estab resp of TP
pcon  resp of TP + relay of TP + resp of TG
get   resp of TP + relay of TP + resp of TG + servicestart of TG
pget  resp of TP + 3/2*relay of TP + 2*resp of TG + servicestart of TG
end   0.5*resp of TP + 0.5*relay of TP + 0.5*resp of TG + serviceend of TG

```

```

total 4.5*resp of TP + 4*relay of TP + 4.5*resp of TG + serviceall of TG
2*end-get          2*servicedata + service(2*stop-start)

```

```

relay: time(data_out) - time(data_in).
resp: response.
serviceend = time intervals(send data) + time intervals(stop this task).

```

A guide to use the result:

- If you want to select a testproxy with the quickest response to you, just sort the result by *estab*.
- If you need a testproxy through which you can get the quickest response from the single *checksite* (see [Section 2.2 \[Startup Options\], page 2](#)), please sort by *pcon* if possible. If include the SERVICE response but not CONNECT response only, use *get* or *pget* instead. Certainly, you can guess the distribution of route from *testproxy* to *checksite* by comparing *pcon* - *estab*, etc.
- On the other hand, if you care for the bandwidth of the whole route to target, you should sort by $2*end - get$. It is not accurate if the data returned by *checksite* is not large enough.

If you still feel puzzled, these tips are for you:

- You can sort testproxies by *estab* if you want to browse webpages via testproxy (either connect to myproxy firstly or not).
This is the common choice if you need quick responses to all of the sites in average.
- You can sort result by *get* or *pget* if you want to browser webpages of the *checksite* (see [Section 2.2 \[Startup Options\], page 2](#)) frequently via testproxy.
It is a good choice if you care the first response from the *checksite* (see [Section 2.2 \[Startup Options\], page 2](#)) only.
- You can set *mytagconreplysize* to a big number, select a suitable *checksite* (a page with large data), and sort testproxies in the result by *end* if you want to download files via testproxy (through myproxy firstly or not) from *checksite*.
Bandwidth but not delay is important to bulk download.

Some of other *proxy hunters* prefer the total delay. From the *approximate mathematics* and the chart, I can't get the same conclusion. **I think the total delay is not as useful as *estab,pcon,pget,get* or even *end*.** If you have some different ideas, please send email to bug-proxyknife@gnu.org.

Tips: The less delay, the more speed. You should select the testproxies with the shortest delay, such as *estab,pcon,get,pget* or *end*.

12 Contact

- Reporting bugs: please send email to bug-proxyknife@gnu.org.
Please send mail to bug-proxyknife-request@gnu.org with no body and a Subject: header line of just "subscribe" to subscribe yourself to this list. Alternatively, you can subscribe yourself to the list at <http://lists.gnu.org/mailman/listinfo/bug-proxyknife>.
- Homepage: <http://www.gnu.org/software/proxyknife/proxyknife.html>.
- Online summary: <http://savannah.gnu.org/projects/proxyknife>.
- Files: <http://ftp.gnu.org/gnu/proxyknife> ,<ftp://ftp.gnu.org/gnu/proxyknife> or other GNU ftp mirrors: <http://www.gnu.org/prep/ftp.html>.
- Email: skyroam@gmail.com.

Appendix A Copying This Manual

A.1 GNU Free Documentation License

Version 1.2, November 2002

Copyright © 2000,2001,2002 Free Software Foundation, Inc.
51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document *free* in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of “copyleft”, which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The “Document”, below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as “you”. You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A “Modified Version” of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A “Secondary Section” is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document’s overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The “Invariant Sections” are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The “Cover Texts” are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License.

A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A “Transparent” copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not “Transparent” is called “Opaque”.

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The “Title Page” means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, “Title Page” means the text near the most prominent appearance of the work’s title, preceding the beginning of the body of the text.

A section “Entitled XYZ” means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as “Acknowledgements”, “Dedications”, “Endorsements”, or “History”.) To “Preserve the Title” of such a section when you modify the Document means that it remains a section “Entitled XYZ” according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document’s license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both

covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its

Title Page, then add an item describing the Modified Version as stated in the previous sentence.

- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the “History” section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled “Acknowledgements” or “Dedications”, Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled “Endorsements”. Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled “Endorsements” or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version’s license notice. These titles must be distinct from any other section titles.

You may add a section Entitled “Endorsements”, provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled “History” in the various original documents, forming one section Entitled “History”; likewise combine any sections Entitled “Acknowledgements”, and any sections Entitled “Dedications”. You must delete all sections Entitled “Endorsements.”

6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an “aggregate” if the copyright resulting from the compilation is not used to limit the legal rights of the compilation’s users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document’s Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled “Acknowledgements”, “Dedications”, or “History”, the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <http://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License “or any later version” applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

A.1.1 ADDENDUM: How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

```
Copyright (C) year your name.
Permission is granted to copy, distribute and/or modify this document
under the terms of the GNU Free Documentation License, Version 1.2
or any later version published by the Free Software Foundation;
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover
Texts. A copy of the license is included in the section entitled ‘‘GNU
Free Documentation License’’.
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the “with...Texts.” line with this:

```
with the Invariant Sections being list their titles, with
the Front-Cover Texts being list, and with the Back-Cover Texts
being list.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.

GNU General Public License

Version 2, June 1991

Copyright © 1989, 1991 Free Software Foundation, Inc.
51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public License is intended to guarantee your freedom to share and change free software—to make sure the software is free for all its users. This General Public License applies to most of the Free Software Foundation’s software and to any other program whose authors commit to using it. (Some other Free Software Foundation software is covered by the GNU Lesser General Public License instead.) You can apply it to your programs, too.

When we speak of free software, we are referring to freedom, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish), that you receive source code or can get it if you want it, that you can change the software or use pieces of it in new free programs; and that you know you can do these things.

To protect your rights, we need to make restrictions that forbid anyone to deny you these rights or to ask you to surrender the rights. These restrictions translate to certain responsibilities for you if you distribute copies of the software, or if you modify it.

For example, if you distribute copies of such a program, whether gratis or for a fee, you must give the recipients all the rights that you have. You must make sure that they, too, receive or can get the source code. And you must show them these terms so they know their rights.

We protect your rights with two steps: (1) copyright the software, and (2) offer you this license which gives you legal permission to copy, distribute and/or modify the software.

Also, for each author’s protection and ours, we want to make certain that everyone understands that there is no warranty for this free software. If the software is modified by someone else and passed on, we want its recipients to know that what they have is not the original, so that any problems introduced by others will not reflect on the original authors’ reputations.

Finally, any free program is threatened constantly by software patents. We wish to avoid the danger that redistributors of a free program will individually obtain patent licenses, in effect making the program proprietary. To prevent this, we have made it clear that any patent must be licensed for everyone’s free use or not licensed at all.

The precise terms and conditions for copying, distribution and modification follow.

TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

0. This License applies to any program or other work which contains a notice placed by the copyright holder saying it may be distributed under the terms of this General Public License. The “Program”, below, refers to any such program or work, and a “work based on the Program” means either the Program or any derivative work under copyright law: that is to say, a work containing the Program or a portion of it, either verbatim or with modifications and/or translated into another language. (Hereinafter, translation is included without limitation in the term “modification”.) Each licensee is addressed as “you”.

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running the Program is not restricted, and the output from the Program is covered only if its contents constitute a work based on the Program (independent of having been made by running the Program). Whether that is true depends on what the Program does.

1. You may copy and distribute verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and give any other recipients of the Program a copy of this License along with the Program.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

2. You may modify your copy or copies of the Program or any portion of it, thus forming a work based on the Program, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:
 - a. You must cause the modified files to carry prominent notices stating that you changed the files and the date of any change.
 - b. You must cause any work that you distribute or publish, that in whole or in part contains or is derived from the Program or any part thereof, to be licensed as a whole at no charge to all third parties under the terms of this License.
 - c. If the modified program normally reads commands interactively when run, you must cause it, when started running for such interactive use in the most ordinary way, to print or display an announcement including an appropriate copyright notice and a notice that there is no warranty (or else, saying that you provide a warranty) and that users may redistribute the program under these conditions, and telling the user how to view a copy of this License. (Exception: if the Program itself is interactive but does not normally print such an announcement, your work based on the Program is not required to print an announcement.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Program, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Program, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Program.

In addition, mere aggregation of another work not based on the Program with the Program (or with a work based on the Program) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may copy and distribute the Program (or a work based on it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you also do one of the following:
 - a. Accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,
 - b. Accompany it with a written offer, valid for at least three years, to give any third party, for a charge no more than your cost of physically performing source distribution,

a complete machine-readable copy of the corresponding source code, to be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange; or,

- c. Accompany it with the information you received as to the offer to distribute corresponding source code. (This alternative is allowed only for noncommercial distribution and only if you received the program in object code or executable form with such an offer, in accord with Subsection b above.)

The source code for a work means the preferred form of the work for making modifications to it. For an executable work, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the executable. However, as a special exception, the source code distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

If distribution of executable or object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place counts as distribution of the source code, even though third parties are not compelled to copy the source along with the object code.

4. You may not copy, modify, sublicense, or distribute the Program except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense or distribute the Program is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.
5. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Program or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Program (or any work based on the Program), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Program or works based on it.
6. Each time you redistribute the Program (or any work based on the Program), the recipient automatically receives a license from the original licensor to copy, distribute or modify the Program subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties to this License.
7. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Program at all. For example, if a patent license would not permit royalty-free redistribution of the Program by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Program.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system, which is implemented by

public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

8. If the distribution and/or use of the Program is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Program under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.
9. The Free Software Foundation may publish revised and/or new versions of the General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Program specifies a version number of this License which applies to it and “any later version”, you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of this License, you may choose any version ever published by the Free Software Foundation.

10. If you wish to incorporate parts of the Program into other free programs whose distribution conditions are different, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

NO WARRANTY

11. BECAUSE THE PROGRAM IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM “AS IS” WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.
12. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

END OF TERMS AND CONDITIONS

Appendix: How to Apply These Terms to Your New Programs

If you develop a new program, and you want it to be of the greatest possible use to the public, the best way to achieve this is to make it free software which everyone can redistribute and change under these terms.

To do so, attach the following notices to the program. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the “copyright” line and a pointer to where the full notice is found.

```
one line to give the program's name and a brief idea of what it does.
Copyright (C) yyyy name of author
```

```
This program is free software; you can redistribute it and/or modify
it under the terms of the GNU General Public License as published by
the Free Software Foundation; either version 2 of the License, or
(at your option) any later version.
```

```
This program is distributed in the hope that it will be useful,
but WITHOUT ANY WARRANTY; without even the implied warranty of
MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the
GNU General Public License for more details.
```

```
You should have received a copy of the GNU General Public License
along with this program; if not, write to the Free Software
Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.
```

Also add information on how to contact you by electronic and paper mail.

If the program is interactive, make it output a short notice like this when it starts in an interactive mode:

```
Gnomovision version 69, Copyright (C) year name of author
Gnomovision comes with ABSOLUTELY NO WARRANTY; for details type 'show w'.
This is free software, and you are welcome to redistribute it
under certain conditions; type 'show c' for details.
```

The hypothetical commands ‘show w’ and ‘show c’ should show the appropriate parts of the General Public License. Of course, the commands you use may be called something other than ‘show w’ and ‘show c’; they could even be mouse-clicks or menu items—whatever suits your program.

You should also get your employer (if you work as a programmer) or your school, if any, to sign a “copyright disclaimer” for the program, if necessary. Here is a sample; alter the names:

```
Yoyodyne, Inc., hereby disclaims all copyright interest in the program
'Gnomovision' (which makes passes at compilers) written by James Hacker.
```

```
signature of Ty Coon, 1 April 1989
Ty Coon, President of Vice
```

This General Public License does not permit incorporating your program into proprietary programs. If your program is a subroutine library, you may consider it more useful to permit linking proprietary applications with the library. If this is what you want to do, use the GNU Lesser General Public License instead of this License.

Index

A

arguments 2

C

chapter,Scripts 15
 checkreqin 4
 checksite 3
 command line 2
 Command-line 2

D

debug 2

E

Examples 10
 Exclusive 2

F

FDL, GNU Free Documentation License 21

G

General Usage 5
 GPL, GNU General Public License 28

H

httpstestmethod 4

I

Invoking 2

K

key 4

L

logfilename 4

M

mode 3
 myconreplysize 4
 myhost 3
 mypass 3
 myport 3
 mytype 3
 myuser 3

O

Option 2
 Options 2
 Output 17

P

proxyknifein 3
 proxyknifeout 5
 proxyknifetype 3
 Proxylist 16

R

rcvtimeo 4

S

sndtimeo 4
 socks4testmethod 4
 socks5testmethod 4
 startup file 10
 Startup File 10
 Startup Options 2

T

testconreplysize 4
 testtagreplysize 4
 threads 3

U

user_agent 3